




Wellon Programmer 64 Bit USB driver install guide

This article has introduced 64 bit USB driver install process under Vista/Win7 system. Now Wellon Programmer 64 Bit USB driver program don't have a digital signature. The method that this article has introduced is the same with other solution for solute other without a digital signature. If 32 bit system prompt haven' t digital signature , you can choose continue installation, need not refer this text.

一、 Disable Driver Signature Enforcement


Start computer, press F8 key, show “Advanced Boot Options”, choose “Disable Driver Signature Enforcement”, and then press enter key to start the computer.

No matter what install or run Wellon software, must set up this option when start the computer. If not site this option you can't use Wellon software normally, the screen will like this:






Pay attention to the window topic, there is no sequence after “Wellon Universal Programmer & Tester” . Normally start will show such as “-1”、“-2” suffix, means this window connect with the first programmer or the second programmer. Without select “Disable Driver Signature Enforcement” , Operating System can’t load programmer driver software. “Device Manager” show:




Device Manager show “!” sign, device properties are shown below:



二、 Install first time or update


From 64 bit Vista system update to Win7 system, maybe display a system compatibility warning.

In the case of the driver is not installed or can't automatically install, the Device Manager appears as "other devices".




Third: manually install the driver

Make sure "other devices" which is list in "Device Manager" show Wellon programmer. Click the right button of the mouse, choose "Update Driver Software", show "Update Driver Software" frame :




Choose “Browse my computer for driver software”, show the following frame:




Click “Browse” button, select the folder that contains drivers for your hardware. The folder that contains drivers for the hardware is under “ \weilei\wellon\usbsys64” .

After select the folder, click “OK” button, and then show “Window Security” frame




Select “Install this driver software anyway”






After install the driver software completely, the window will show:




After install the driver software normally or during run software, may be show the following warning:




Click “Close” button, the warning have no affect to running the program software.


After install the driver software completely, “Universal Serial Bus controllers” will show as below:



Click the right button of the mouse, select “Property” then show “Wellon usb programmer Properties” and driver details:



Install the driver normally and chose the “Disable Driver Signature Enforcement” at the begin of start the Operating System, then start Wellon software, the window topic will have such as “-1”、“-2” suffix.



If there is no number suffix such as “-1”、“-2” on Window topic, Wellon programming software can’t find the corresponding programmer.